Release GC-Prevue v20.2 Notes

Table of Contents

ENHANCED FEATURES	2
RS-274X IMPORT	2
On Line Help	2
ITEMS FIXED SINCE V20.1.4	3

Enhanced Features

RS-274X import

A switch has been added to allow the correct image to be presented if the RS-274X file being imported incorrectly assumes the Macro21 primitive center is the point of rotation. The updated RS-274X specification now explicitly describes the correct interpretation of custom aperture macros and it is expected that this option will be very rarely needed by users.

On Line Help

All products have finally had their On Line Help files updated to the HTMLHelp format, allowing the Help file to appear within the product again.

Items Fixed since v20.1.4

.

This list is customer reported issues fixed for this release.

#114 Added an option allowing the correct handling of incorrectly formatted RS-274X data.
#103 Missing and duplicated toolbar buttons have been added or modified to correctly present a valid toolbar button for all functions.